

# Upgrade Guide

---

This article describes how to update Agiloft to a newer version. To identify the versions of the application being upgraded, see [Release Version Numbering](#).



If you are running a version of Agiloft with a release date prior to 2017\_01 or 2019\_01, you must install a minimum required version of Agiloft before you can upgrade to the current version.

## Process Overview

In general, the update process has the following steps:

1. **Back up** everything that should be backed up. This might include KBs, software code, database files, etc., depending on what is to be updated.
2. Obtain new licenses for the new release, if it is a major upgrade with a new main version number.
3. Perform the upgrade.

For moderately sized KBs, the process is simple because the installer includes an option to create a full backup, and it automatically executes a set of integrity checks after the upgrade. In the rare case that something goes wrong and the system can't repair itself, it automatically **rolls back** to the pre-update state using the backup.

Regardless of KB size, the upgrade itself is typically quick. In larger KBs, the overall process can take a long time due to the time required to create a backup.



For in-house systems, and for more information about creating backups more easily for large KBs, see [Upgrading In-House Systems](#).

## Update Methods

There are three ways to run the update process:

- **Online Update.** This uses an online connection to download and install the newest version of Agiloft. This is the simplest method, provided you have a stable internet connection.
- **Manual Update.** You download the installation files and install them locally. This option is preferred if your connection is unstable, or if you want to minimize the potential for errors.
- **EWUpdate Command Line Utility.** This option is generally not necessary, but it can be useful for advanced functions, or in situations where the online and manual methods are unsuccessful.

# Preparing to Upgrade

---

Before you upgrade on a Windows server:

- Open the command prompt as an Administrator and restart the Agiloft services. This clears up any long-waiting threads in the application or database process that might affect the upgrade. Here is an example of the command to use: `C:\Agiloft\bin\ew-control.exe -a restart`
- Sign all other users out of that Windows server, aside from the user that runs the upgrade. This prevents other Windows users from interfering with the upgrade process, particularly while restarting services or accessing files and folders.

# Minimum Required Versions

---

If you don't install every new version as it's released, you might need to upgrade to a minimum required version before proceeding to the current version of Agiloft. Review the list below and start by installing the earliest version of Agiloft that you don't yet have. You might need to install multiple minimum versions before you can upgrade to the current version of Agiloft. For example, if you're running version 2016\_02 and want to upgrade to 2019\_02, you must first install the minimum required version 2017\_01, then the next minimum required version 2019\_01, before finally upgrading to 2019\_02.

## Version 2019\_01

---

If you're running a version of Agiloft with a release date prior to 2019\_01, you must upgrade to the 2019\_01 release before installing a later version.

1. Download the 2019\_01 installer package from <https://download.agiloft.com/upgrade/>.



You cannot upgrade to version 2019\_01 using the in-system Software Update option. You must download and run the installer package to upgrade to 2019\_01.

2. Stop and disable the DHCP Client and Windows Event Log services, using the Services program or the Services tab of Task Manager. Make sure to disable them, not just stop them, so that they don't start running again during the upgrade.
3. Upgrade your system to 2019\_01.
4. After the successful upgrade, upgrade to the current version of Agiloft, releases 2019\_02 and later. You can enable the DHCP Client and Windows Event Log services at this point.

## Version 2017\_01

---

If you're running a version of Agiloft with a release date prior to 2017\_01, you must upgrade to the 2017\_01 release before installing a later version.

1. Download the 2017\_01 installer package from [https://download.agiloft.com/archive/2017\\_01/](https://download.agiloft.com/archive/2017_01/).
2. Stop and disable the DHCP Client and Windows Event Log services, using the Services program or the Services tab of Task Manager. Make sure to disable them, not just stop them, so that they don't start running again during the upgrade.
3. Upgrade your system to 2017\_01.
4. After the successful upgrade, upgrade to the next minimum version of Agiloft, version 2019\_01. You can enable the DHCP Client and Windows Event Log services at this point.

# Online Update

---

The online update option is the simplest method.

1. Stop and disable the DHCP Client and Windows Event Log services, using the Services program or the Services tab of Task Manager. Make sure to disable them, not just stop them, so that they don't start running again during the upgrade.
2. Run the **Setup Assistant** in your installation directory and select Software Update from the main menu, then click Check for updates online.

## **Agiloft Software Update**

Software update helps you keep your copy of Agiloft up to date.

**Please select how you wish to update the product:**

### **Check for updates online**

This is ideal if you have a medium or high-speed Internet connection. The Setup Wizard will check the Agiloft website and download any updates z

### **Manual update**

You can also download new Agiloft versions manually. If so, just run installer to perform the update.

- 3.
4. Setup automatically checks for a new version of Agiloft. If a new version is available, the Setup Assistant downloads it and starts the update.

Checking for available updates at [www.agiloft.com](http://www.agiloft.com)

Downloading: 1% complete


5. The user can monitor and set update options using the web interface.

# Manual Update

---

If you aren't installing Agiloft for the first time, you can update the software by simply downloading and installing the latest version. The latest official release of Agiloft can be found at <https://www.agiloft.com/ewdownload/>.

1. Stop and disable the DHCP Client and Windows Event Log services, using the Services program or the Services tab of Task Manager. Make sure to disable them, not just stop them, so that they don't start running again during the upgrade.
2. Run the downloaded installer. The installer detects an existing Agiloft instance and prompts the user about a possible update.



Setup Installer detects installed version

3. Confirm the selections on the **Update Options** screen. These options include whether to run a backup; whether to delete backup files after the update; and whether to preserve modified MySQL parameters. The update options are explained in more detail in **Command Line Options**. If you aren't familiar with the commands, be cautious in changing the default selections, particularly if you are working with a live system.
4. Follow the steps in the installer to complete the upgrade.

# EWUpdate Command Line Utility

The EWUpdate utility works the same way as the manual installer, but runs from the command line. If you run the utility with no options, it performs an update with all default options selected. If you need to change the options for the utility, use the command line options listed below.

✔ Use the `--help` option (`ewupdate --help`) to see all the commands you can use with the utility.

## Command Line Options

These options are available in the manual installer and in the EWUpdate command line utility. Default options can be changed using the command-line options listed, which correspond to the options presented in the installer. The list below consists of the most commonly recommended options.

Update option	Corresponding EWUpdate command-line option	Description
Backup database data using OS-level backup	<code>-k,--skiposlevel</code>	This command only applies if the built-in MySQL server is used. Under normal circumstances a full OS-level backup is made. Use this option to skip the default OS-level backup of the MySQL directory. No database restoration is possible if the upgrade fails.
Skip checkers unless any patchers were run	<code>-p,--scup</code>	When the application server starts, it performs data checks for consistency, which might take a long time. Use this option to skip data checking if no data was changed on update. This can speed the time taken to start the application server.
Skip project backup if possible	<code>-K,--skipprjbckp</code>	At the very beginning of the update process all existing projects are saved to the backup directory. If this option is set then no project backup is performed, if allowed. Some update modes require a project backup, in which case it isn't skipped.
Don't delete temporary files after update	<code>-t,--keeptemp</code>	During the update, temporary files are normally stored on the hard drive. These may include data backups, unpacked new code, etc. By default, temporary files are removed after an update. If this option is set, temporary files are left on the device. The temporary files are automatically deleted before the next update.

Don't backup temporary files - logs etc	-i,--backuptemp	If this option is set then no temporary files such as log files are backed up before the update. This saves used disk space and shortens the update time.
---	-----------------	---

For additional update options, use the `--help` command to print a full list of commands.

Example: `ewupdate --stable`

```

-s,--stable          Download stable release version (Official Release)
-d,--devel           Download development version (Alpha)
-C,--custom <host>   Download from custom server
-F,--file <file>     Upgrade from a distribution that has already been
downloaded to the local hard drive
-f,--force           Unattended update, all prompts are answered 'yes'
-c,--caution         Unattended update, all prompts are answered 'no'
-k,--skiposlevel     Skip OS level backup (avoid using this when skipping
project backup)
-K,--skipprjbckp     Skip project backups (avoid using this when skipping OS
level backup)
-t,--keeptemp        Keep temp files
-p,--scup            Skip checkers unless patchers were run
-i,--backuptemp       Backup temporary files such as logs (when unattended mode)
-r,--requiredspace <Gb> Disk space (Gb) required for update (use with care)
-w,--warn <MMM or MMM:NNN> Displays a warning message to customers about an
impending update. Argument syntax is MMM or MMM:NNN, where MMM is the number of
minutes before update and NNN is the estimated update duration in minutes
-A,--allowsameversion Do update even if new version is same as old one
-X,--forceincompat    Forces an upgrade between releases that should not be
compatible. Do not use this option.
-v,--verbose          Print error details
-h,--help             Prints this help

```

# Rolling Back

---

If the upgrade fails, the system automatically troubleshoots problems and applies the proper fixes. If the upgrade still fails, the system prompts the user for input before rolling back to the pre-update version. All your settings are retained, and the logs are copied to <Agiloft-Home>\logs\ so you can use them to trace the cause of the failure and resolve it before trying the upgrade again.